

CONFIGURATION 801 IN THE CYCLE 38 OF ARPEGE/IFS.

YESSAD K. (METEO-FRANCE/CNRM/GMAP/ALGO)

November 10, 2011

Contents

1	Introduction and purpose.	4
2	Algorithm of this configuration.	5
2.1	Notations.	5
2.2	Case without any minimization.	5
2.3	Case with minimization.	6
2.4	Aspect of the function f	6
3	The sequences of STEPO called.	7
3.1	General architecture under STEPO.	7
3.2	Example of sequences of STEPO, STEPOTL and STEPOAD called in a configuration 801 ARPEGE/IFS run with N_{stop} timesteps.	8
3.3	Example of sequences of STEPO, STEPOTL and STEPOAD called in a configuration 801 ALADIN run with N_{stop} timesteps.	10
4	Organigramme.	11
4.1	Features other than SIM4D.	11
4.2	The simulator SIM4D.	13
4.3	Action of each routine.	13
5	List of useful variables.	15
5.1	YOMCT0 and NAMCT0.	15
5.2	YOMIOP and NAMTRAJP.	15
5.3	YOMLCZ and NAMLCZ.	15
5.4	YOMSENS and NAMSSENS.	17
5.5	YOMVAR and NAMVAR.	17
5.6	YOMVRTL and NAMVRTL.	17
6	Example of namelist.	18
7	References and internal notes.	26
7.1	Publications.	26
7.2	Some internal notes and other ARPEGE notes.	26

Abstract:

This documentation describes the algorithmic and technical aspects of the configuration 801 of ARPEGE/IFS, which allows in particular to do sensitivity studies. An example of namelist is provided.

1 Introduction and purpose.

This configuration is used to do sensitivity studies and can help to answer to the two following questions:

- Defining a scalar cost function (preferably a quadratic one), what is the sensitivity of this cost function to some basic meteorological variables (for example the state variables of the model)? What are the basic variables which have the most impacts on this cost function?
- One does a forecast (“experiment forecast”), and uses a “reference forecast”. The question is: what is the perturbation to bring to the initial state, in order the model forecast to get the closest as possible as the “reference forecast”?

At least the adjoint code is used in this configuration, and some particular options of this configuration also use the tangent linear code. Such a configuration has been briefly described in some papers or internal documentations, for example (NTA28), (Rabier et al., 1996) or (Soci et al, 2003). A more detailed documentation (ID801O) has been provided in the past but it has not been updated since 1995; most aspects of this documentation remain valid for cycle 38 and cycle AL38. One currently tries to give a more detailed updated description of this configuration.

* **Modifications since cycle 37:** none

2 Algorithm of this configuration.

The direct model is defined by the primitive equations model, but it would be possible to do sensitivity experiments on a 2D shallow-water model or on a 3D non-hydrostatic model (currently not yet coded).

2.1 Notations.

- U (resp. V): components of the horizontal wind.
- D is the horizontal wind divergence.
- χ is the velocity potential ($D = \nabla^2 \chi$).
- ζ is the horizontal wind vorticity.
- ψ is the stream function ($\zeta = \nabla^2 \psi$).
- T is the temperature.
- T_{ST} is the standard atmosphere temperature.
- q is the humidity.
- Π is the hydrostatic pressure.
- Π_{ST} is the standard atmosphere hydrostatic pressure.
- Π_{s} is the hydrostatic surface pressure.
- c_p is the specific heat at constant pressure for air.
- L_v is the latent heat vaporisation constant for water.
- A_{Π} is a constant to make homogeneous the formula defining f .
- $K_{\psi}, K_{\chi}, K_U, K_V, K_T, K_q, K_{\Pi}$ are coefficients (generally 0 or 1) allowing to select only a subset of variables in function f .

2.2 Case without any minimization.

The simplest case to study is the case where one wants to answer the first question: once defined a scalar cost function (preferably a quadratic one), what is the sensitivity of this cost function to some basic meteorological variables (for example the state variables of the model)? No minimization is involved in this case, and only the direct and adjoint codes are used, excepted for particular applications where the cost function is defined on a limited area (in this case the tangent linear code may be sometimes called).

It follows the following steps, using the direct and the adjoint codes. The forecast is assumed to have N_{stop} timesteps. One provides an initial situation (vector \mathbf{X}_0) and a reference analysis or forecast valid for the instant $t = t_{N_{\text{stop}}}$ (vector $\mathbf{Y}_{N_{\text{stop}}}$).

- The initial step is denoted by the vector of state variables \mathbf{X}_0 . The forecast direct integration provides the steps $\mathbf{X}_1, \mathbf{X}_2, \dots, \mathbf{X}_{N_{\text{stop}}}$. These quantities are used as a trajectory for the adjoint integrations. The components of vector \mathbf{X} are x_i . The model integration is symbolically denoted by

$$\mathbf{X}_{N_{\text{stop}}} = \mathcal{M}_{0 \rightarrow N_{\text{stop}}} \mathbf{X}_0$$

- One has also another final state $\mathbf{Y}_{N_{\text{stop}}}$ which is a priori different from $\mathbf{X}_{N_{\text{stop}}}$. That can be another forecast, or an analysis. The difference between $\mathbf{X}_{N_{\text{stop}}}$ and $\mathbf{Y}_{N_{\text{stop}}}$ is assumed to be not too big and is denoted by $[\delta \mathbf{Y}]_{N_{\text{stop}}}$.
- Let us define a scalar function of \mathbf{X} : $f(\mathbf{X})$. See paragraph 2.4 for examples of available functions in ARPEGE/IFS and ALADIN. This is the ‘‘cost function’’. One computes $f([\delta \mathbf{Y}]_{N_{\text{stop}}})$.
- Applying the adjoint model to the perturbation $(\delta \mathbf{Y})_{N_{\text{stop}}}$ provides the gradient of the cost function with respect to the initial state.

$$\nabla f = \mathcal{M}_{0 \rightarrow N_{\text{stop}}}^* [\delta \mathbf{Y}]_{N_{\text{stop}}}$$

where $\mathcal{M}_{0 \rightarrow N_{\text{stop}}}^*$ is the adjoint operator of $\mathcal{M}_{0 \rightarrow N_{\text{stop}}}$.

2.3 Case with minimization.

We now want to answer the second question: what is the perturbation to bring to an initial state, in order the model forecast to get the closest as possible as the “reference forecast”? One follows the previous algorithm, but additionally an iterative scheme is performed as follows:

- define a perturbation $[\delta\mathbf{X}]_0(iter = 0)$.
- run the direct model, taking now as initial state $\mathbf{X}_0 + [\delta\mathbf{X}]_0(iter = 0)$, then the adjoint model.
- computation of f and its gradient also to determine the next value $[\delta\mathbf{X}]_0(iter = 1)$ to test.
- run the direct model, taking now as initial state $\mathbf{X}_0 + [\delta\mathbf{X}]_0(iter = 1)$, then the adjoint model.
- etc...

The algorithm stops when $[\delta\mathbf{X}]_0(iter)$ is close enough to the searched solution or when the maximum number of iterations we have previously pre-defined is reached. Note that one can replace at this stage the direct integration by a tangent linear integration from the initial perturbation $[\delta\mathbf{X}]_0(iter)$. This algorithm looks like a 4D-VAR problem but it is simpler: no observation, the cost-function has only one component and the guess is replaced by a forecast (or an analysis) at instant $t_{N_{stop}}$ (that means in particular that contrary to the 4D-VAR assimilation there is no interpolation at some observation points which are not points of the Gaussian grid).

2.4 Aspect of the function f .

This is a scalar function of the model state variables, a quadratic one being desirable. Three choices are currently available (variable **NJROPT**):

- **NJROPT=1**: the following quadratic one:

$$f(\psi, \chi, T, q, \log \Pi) = 0.5 \int_{\mathcal{D}} (K_{\psi}\psi^2 + K_{\chi}\chi^2 + K_{Tc_p}T^2 + K_q L_v q^2) ds d(\log \Pi) + 0.5 \int_{\mathcal{D}_s} K_{\Pi} A_{\Pi} (\log \Pi)^2 ds$$

- **NJROPT=2**: a linear one:

$$f(U, V, T, q, \Pi) = 0.5 \int_{\mathcal{D}} \left(K_U \frac{U}{U_r} + K_V \frac{V}{V_r} + K_T \frac{(T - T_{ST})}{T_r} + K_q \frac{q}{q_r} \right) ds \frac{d\Pi}{\Pi_{sr}} + 0.5 \int_{\mathcal{D}_s} K_{\Pi} \frac{(\Pi - \Pi_{ST})}{\Pi_{sr}} ds$$

In practical: $U_r = V_r = 1$ m/s; $T_r = 1$ K; $q_r = 1$ g/m³; $\Pi_{sr} = 101325$ Pa.

- **NJROPT=3**: an enstrophy cost-function.

$$f(\psi) = 0.5 \int_{\mathcal{D}} \psi^2 ds d(\log \Pi)$$

This is a sub-option of the quadratic function defined for **NJROPT=1**.

This function can be zeroed out of a pre-defined domain. \mathcal{D} is the domain where f is non-zero, \mathcal{D}_s is the surface projection of \mathcal{D} . This possibility is interesting for example to do sensitivity studies in a limited region.

3 The sequences of STEPO called.

3.1 General architecture under STEPO.

```
control/STEPO ->
* Gestion of read/write: utility/IOPACK
* Inverse spectral transforms: transform/TRANSINVH -> TRANSINV_MDL
* Grid point computations: control/SCAN2H -> control/SCAN2M
* Direct spectral transforms: transform/TRANSDIRH -> TRANSDIR_MDL
* Spectral computations: control/(E)SPCM (see below).
```

The sequences of call to **STEPO** are controlled by a variable (often called **CDCONF** or **CLCONF**) containing 9 letters or zeros [L1][L2][L3][L4][L5][L6][L7][L8][L9]

- L1 controls the file write/read.
- L2 controls the inverse Legendre transforms.
- L3 controls the inverse Fourier transforms.
- L4 controls the grid-point computations for dynamics and physics.
- L5 controls the grid-point computations for post-processing.
- L6 controls the grid-point computations for assimilation.
- L7 controls the direct Fourier transforms.
- L8 controls the direct Legendre transforms.
- L9 controls the spectral computations.

For example a model integration time-step is defined by the sequence [L1]AAA00AAA.

The tangent linear and adjoint codes of **STEPO** are respectively **STEPOTL** and **STEPOAD**.

3.2 Example of sequences of STEPO, STEPOTL and STEPOAD called in a configuration 801 ARPEGE/IFS run with N_{stop} timesteps.

* **Case L801TL=.F.; LMINI=.F.:**

SIMULO (SIM4D called by CGR1):

```

-----
TAAA00AAA STEPO      (jstep=1)
.....
TAAA00AAA STEPO      (jstep=Nstop)
-----
B00000000 STEPO
-----
OK0000000 STEPO
OGB0L0AA0 STEPOTL
OGB0L0AA0 STEPOAD
-----
A00000000 STEPO
-----
OE0000000 STEPO      (jstep=Nstop)
OAAA00AAA STEPOAD
.....
OE0000000 STEPO      (jstep=1)
OAAA00AAA STEPOAD
-----
A00000000 STEPO
O00000000 CNT0
-----

```

- First the model runs N_{stop} sequences of type 'TAAA00AAA STEPO': this is the direct model which computes the trajectory; the trajectory is written on a buffer ([L1]='T').
- The model then reads $\mathbf{Y}_{N_{\text{stop}}}$ on a file called 'ICMRF[cojo]0000' and it computes $[\delta\mathbf{Y}]_{N_{\text{stop}}} = \mathbf{X}_{N_{\text{stop}}} - \mathbf{Y}_{N_{\text{stop}}}$ (sequence 'B00000000 STEPO').
- The sequence 'OK0000000 STEPO' + 'OGB0L0AA0 STEPOTL' + 'OGB0L0AA0 STEPOAD' is called only if the cost-function is non-zero in a limited subdomain (**LOCNORM=.T.**).
- The vector of components $[\partial f/\partial y_i]_{N_{\text{stop}}}$ is written on file 'MG[cojo]000+[Nstop]' (sequence 'A00000000 STEPO'). [Nstop] is coded on 4 digits.
- The model then runs N_{stop} sequences of type 'OE0000000 STEPO + OAAA00AAA STEPOAD' ('OE0000000 STEPO' converts the spectral trajectory into grid-point space, 'OAAA00AAA STEPOAD' calls the adjoint model).
- The vector of components $[\partial f/\partial y_i]_0$ is written on file 'MG[cojo]000+0000' (sequence 'A00000000 STEPO').

* **Case L801TL=.T.; LMINI=.F.:** This case seems have no significant interest compared to the previous one; the only differences noticed are that the sequence 'B00000000 STEPO' is replaced by a sequence 'V00000000 STEPO' and that the sequence 'A00000000 STEPO' writing $[\partial f/\partial y_i]_{N_{\text{stop}}}$ on file 'MG[cojo]000+[Nstop]' disappears.

* Case L801TL=.F.; LMINI=.T.:

```

SIMUL_0 (SIM4D called by CGR1):
-----
TAAA00AAA STEP0      (jstep=1)
.....
TAAA00AAA STEP0      (jstep=Nstop)
-----
B00000000 STEP0
-----
OK0000000 STEP0
OGBOLOAAO STEPOTL
OGBOLOAAO STEP0AD
-----
A00000000 STEP0
-----
OE0000000 STEP0      (jstep=Nstop)
OAAA00AAA STEP0AD
.....
OE0000000 STEP0      (jstep=1)
OAAA00AAA STEP0AD
-----
A00000000 STEP0
O00000000 CNT0
-----

SIMUL_1 to SIMUL_Nsimul (SIM4D called by the minimizer):
do jsimul=1 to Nsimul
-----
TAAA00AAA STEP0      (jstep=1)
.....
TAAA00AAA STEP0      (jstep=Nstop)
-----
B00000000 STEP0
-----
OK0000000 STEP0
OGBOLOAAO STEPOTL
OGBOLOAAO STEP0AD
-----
A00000000 STEP0
-----
OE0000000 STEP0      (jstep=Nstop)
OAAA00AAA STEP0AD
.....
OE0000000 STEP0      (jstep=1)
OAAA00AAA STEP0AD
-----
A00000000 STEP0
-----
enddo

```

The sequences under 'SIMUL_0' are identical to those done in the case **LMINI=.T.**, but there is an additional minimization (minimizing the function f) which launches N_{simul} times the same list of sequences. If the function f has a quadratic expression of $[\delta\mathbf{X}]_{N_{\text{stop}}}$, it has no longer a quadratic expression of the unknown $[\delta\mathbf{X}]_0$ because the model is non-linear. So the minimizer which is used must be valid to minimize non-quadratic functions (the code currently sticks to the minimizer **M1QN3** which uses a quasi-Newton method and can be applied to non-quadratic functions). For more details about the algorithms of minimization, see documentation (IDMINI). Note that the number of simulations N_{simul} can be above the number of iterations of the minimization (this is generally the case for **M1QN3**).

* Case **L801TL=.T.;** **LMINI=.T.:**

```

SIMUL_0 (SIM4D called by CGR1):
-----
TAAA00AAA STEPO      (jstep=1)
.....
TAAA00AAA STEPO      (jstep=Nstop)
-----
B00000000 STEPO
-----
OK0000000 STEPO
OGBOLOAAA STEPOTL
OGBOLOAAA STEPOAD
-----
A00000000 STEPO
-----
OE0000000 STEPO      (jstep=Nstop)
OAAA00AAA STEPOAD
.....
OE0000000 STEPO      (jstep=1)
OAAA00AAA STEPOAD
-----
A00000000 STEPO
000000000 CNT0
-----
SIMUL_1 to SIMUL_Nsimul (SIM4D called by the minimizer):
do jsimul=1 to Nsimul
-----
OE0000000 STEPO      (jstep=1)
OAAA00AAA STEPOTL
.....
OE0000000 STEPO      (jstep=Nstop)
OAAA00AAA STEPOTL
-----
V00000000 STEPO
-----
OK0000000 STEPO
OGBOLOAAA STEPOTL
OGBOLOAAA STEPOAD
-----
A00000000 STEPO
-----
OE0000000 STEPO      (jstep=Nstop)
OAAA00AAA STEPOAD
.....
OE0000000 STEPO      (jstep=1)
OAAA00AAA STEPOAD
-----
A00000000 STEPO
-----
enddo

```

The main differences compared to the case (**L801TL=.T.;** **LMINI=.T.**) are that the sequences 'TAAA00AAA STEPO' calling the direct model have been replaced by sequences 'OE0000000 STEPO' (transformation of the trajectory into grid-point space) + 'OAAA00AAA STEPOTL' (tangent-linear model), and that the sequence 'B00000000 STEPO' has been replaced by 'V00000000 STEPO'. If the function f has a quadratic expression of $[\delta\mathbf{X}]_{N_{\text{stop}}}$, it has also a quadratic expression of $[\delta\mathbf{X}]_0$: that would be enable to use efficient minimizers valid to quadratic functions. The code currently sticks to the minimizer **M1QN3** which uses a quasi-Newton method and can be applied to non-quadratic functions. The solution found for $[\delta\mathbf{X}]_0$ assumes that the model is quasi-linear, and is less exact than the one found with **L801TL=.F.** . The only interest to use (**L801TL=.T.;** **LMINI=.T.**) seems to find $[\delta\mathbf{X}]_0$ more efficiently.

3.3 Example of sequences of STEPO, STEPOTL and STEPOAD called in a configuration 801 ALADIN run with N_{stop} timesteps.

Sequences are generally the same as for ARPEGE. Setting **LWREINI=.T.** (currently maintained in ALADIN only) additionally writes $\mathbf{X}_{j=0} - R_{\text{dx}} \mathcal{M}_{0 \rightarrow N_{\text{stop}}}^* (\delta\mathbf{Y})_{N_{\text{stop}}}$ on file 'ICMSH[cojo]+0000' (this works at least for case **LMINI=.F.**). R_{dx} is a constant set-up in variable **RDX**. Cases **L801TL=.T.** and **LMINI=.T.** have not be recently validated.

4 Organigramme.

4.1 Features other than SIM4D.

Only the main features of the organigramme are described; the “deepest” routines are often omitted.

* CNT0:

CNT0 ->

- * SUOYOMA (0-level setup, part A) -> (comprehensive organigramme not detailed)
 - SUCTO (reads NAMCTO)
 - SUOPHY (reads NAMTRAJP)
 - SUVAR (reads NAMSENS, NAMVAR and NAMVRTL)
- * SUOYOMB (0-level setup, part B) -> (comprehensive organigramme not detailed)
 - SULCZ or SUELCZ (reads NAMLCZ)
- * CGR1 (main control routine for conf 801) -> (see below)

* CGR1:

CGR1 ->

- * part 1:
 - ALLOCATE_CTLVEC
 - SU1YOM ->
 - * SUINIF ->
 - SUGRIDF + SUGRIDU + SUGRIDO
 - SPECRT (ARPEGE) or ESPECRT (ALADIN)
 - * SUVAZX -> SUINIF + CHAVAR
 - * SUSPEC + SUGRIDF + SUGRIDU if .NOT.L801TL (reading files)
 - * SUCOS -> SUJR
- * part 2:
 - SUALLT7 if L801TL
 - CNT2 if L801TL ->
 - * SU2YOM
 - * SUALLT -> ALLOCATE_TRAJECTORY
 - * CNT3 ->
 - CSTA (if LNF)
 - UPSPEC (if LOBSC1)
 - CNMI or FLTMODE (if NMI initialisation)
 - DFI (if DFI initialisation)
 - CNT4 -> (see below)
 - SUSLB if (L801TL or LETRAJP)
 - SUALLT -> ALLOCATE_TRAJECTORY
 - SIM4D -> (see below)
 - SCAAS
- * part 3:
 - GRTEST if LTEST -> (organigramme not detailed)
 - EWREINI if (LELAM and LWREINI) ->
 - * ALLOCATE_CTLVEC
 - * CAIN
 - * STEPO('A00000000') -> (see section about STEPO)
 - * DEALLOCATE_CTLVEC
- * part 4 if (LMINI and .NOT.L801TL)
 - ALLOCATE_CTLVEC
 - SUHESS -> (organigramme not detailed)
 - M1QN3 (Quasi Newton minimisation)
 - CAIN
 - STEPO('A00000000') -> (see section about STEPO)
 - SIM4D -> (see below)
 - SCAAS
 - DEALLOCATE_CTLVEC
- * part 5 if (LMINI and L801TL)
 - ALLOCATE_CTLVEC
 - SUHESS -> (organigramme not detailed)
 - M1QN3 (Quasi Newton minimisation)
 - SCAAS
 - GRTEST -> (organigramme not detailed)
 - DEALLOCATE_CTLVEC
- * final deallocation
 - DEALLOCATE_CTLVEC

* CNT3:

CNT3 ->

- * CSTA (if LNF, in ARPEGE only) -> SUINIF ->
 - SUGRIDF + SUGRIDU + SUGRIDO
 - SPECRT (ARPEGE) or ESPECRT (ALADIN)
- * ELSAC (in ALADIN) -> (organigramme not detailed)
- * UPSPEC (if LOBSC1)
 - RDFPINC -> (organigramme not detailed)
 - STEPO('T00000000') -> (see section about STEPO)
- * CNMI or FLTMODE (if NMI initialisation, in ARPEGE only) -> (organigramme not detailed)
- * DFI (if DFI initialisation, in ARPEGE only) -> (organigramme not detailed)
- * CNT4 ->
 - Prepare occurrences of I/O events:
 - * MONIO + MONVAR + (MOEVAR if ALADIN)
 - Direct integration (features about diagnostics are omitted):
 - * SUALLAVT (if LAVARC and LLWRTRA)
 - * UPDTIM -> (organigramme not detailed)
 - * SUNHSI, SUHEG (for SI scheme)
 - * SUHDU (for horizontal diffusion)
 - * SURAND2
 - * AVARCT -> SUSPEC
 - * READ_TRAJECTORY + GET_TRAJ_SPEC
 - * STEPO('TAAA00AAA') -> (see section about STEPO)

* CNT3TL:

CNT3TL ->

- * SU3YOM
- * CSTA (if LNF) -> SUINIF ->
 - SUGRIDF + SUGRIDU + SUGRIDO
 - SPECRT (ARPEGE) or ESPECRT (ALADIN)
- * CNMITL or FLTMODE (if NMI initialisation) -> (organigramme not detailed)
- * CNT4TL ->
 - Prepare occurrences of I/O events:
 - * MONIO + MONVAR + (MOEVAR if ALADIN)
 - Direct + TL integration (features about diagnostics are omitted):
 - * UPDTIM -> (organigramme not detailed)
 - * SUNHSI, SUHEG (for SI scheme)
 - * ELSINOTA -> (organigramme not detailed)
 - * SUHDU (for horizontal diffusion)
 - * GET_TRAJ_SPEC
 - * STEPO('B00000000') -> (see section about STEPO)
 - * STEPO('OK0000000') -> (see section about STEPO)
 - * STEPOTL('OGBOLOAAA') -> (see section about STEPO)

* CNT3AD:

CNT3AD ->

- * SU3YOM
- * CDSTA -> SUSPEO
- * CNT4AD ->
 - Prepare occurrences of I/O events:
 - * MONIO + MONVAR + (MOEVAR if ALADIN)
 - * STEPO('B00000000') -> (see section about STEPO)
 - * COSTRA ->
 - COSJR (ARPEGE) or ECOSJR (ALADIN) if NJROPT=1 ->
(STEPO('OK0000000') + STEPOTL('OGBOLOAAA') + STEPOAD('OGBOLOAAA') if LOCNORM=T)
 - COSJL if NJROPT=2 -> (organigramme not detailed).
 - COSENS if NJROPT=3 -> (organigramme not detailed).
 - Adjoint integration (features about diagnostics are omitted):
 - * GET_TRAJ_SPEC
 - * UPDTIM -> (organigramme not detailed)
 - * SUNHSI, SUHEG (for SI scheme)
 - * SUHDU (for horizontal diffusion)
 - * ELSINOTA -> (organigramme not detailed)
 - * STEPO('OE0000000') -> (see section about STEPO)
 - * STEPOAD('OAAA00AAA') -> (see section about STEPO)
- * CNMIAD (if NMI initialisation) -> (organigramme not detailed)

4.2 The simulator SIM4D.

This routine is the simulator needed for example in the 3D-VAR or in the 4D-VAR algorithm. It computes the cost-function and its gradient by calling the model and its adjoint. Some deepest callees are omitted (for example the organigramme of CHAVAR and CHAVARIN are not detailed). A detailed description of this simulator is given in documentation (IDVAR).

```
SIM4D ->
* 1/ Initialize:
  - MONVAR
  - SU2YOM
  - SUCOS -> SUJR
  - FJVARBC
  - SUALLT
* 2/ Fill SPA3 by the control variable and come back to physical space:
  - SUSPEC
  - ALLOCATE_CTLVEC + CHAVAR + CAIN + DEALLOCATE_CTLVEC
  - CHAVARIN
  - SBSFGS (if L801TL)
  - ALLOCATE_CTLVEC + CAININ + CHAVARIN + DEALLOCATE_CTLVEC (if L801TL and LBACKG)
  - STEPO('A00000000') -> (see section about STEPO)
* 3/ Tangent linear integration if L801TL:
  - ALLOCATE_CTLVEC + LCNORTL + CAIN + DEALLOCATE_CTLVEC
  - CNT3TL -> (see organigramme under CNT3TL)
* 3b/ Direct integration if .NOT.L801TL:
  - CNT3 -> (see organigramme under CNT3)
* 4/ Adjoint integration:
  - CNT3AD -> (see organigramme under CNT3AD)
* 5/ Come back to control variable space:
  - CHAVARINAD
* 6/ Sum up cost function, release space for trajectory:
  - DEALLT
  - EVCOST
  - SCAAS
```

4.3 Action of each routine.

- **ALLOCATE_CTLVEC**: allocation of **CONTROL_VECTOR** type variables.
- **ALLOCATE_TRAJECTORY**: allocation of some arrays used to store the trajectory needed for TL and AD model.
- **AVARCT**: used in variational assimilation of corrections.
- **CAIN**: canonical injection.
- **CAININ**: inverse of canonical injection.
- **CGR1**: controls the sensitivity job at level 1.
- **CHAVAR**: change of variable used for example in the variational assimilation.
- **CHAVARIN**: inverse action of **CHAVAR**.
- **CNMI**: control routine for normal mode initialization.
- **CNT2**: control routine at level 2.
- **CNT3**: control routine at level 3.
- **COSENS**: computes the cost-function if **NJROPT=3**.
- **COSJL**: computes the cost-function if **NJROPT=2**.
- **COSJR** (**ECOSJR** for ALADIN): computes the cost-function if **NJROPT=1**.
- **COSTRA**: computes the cost-function and its gradient.
- **CSTA**: control routine for reading the file of initial conditions.

- **DEALLOCATE_CTLVEC**: deallocation of **CONTROL_VECTOR** type variables.
- **DFI**: control routine for digital filter initialization.
- **EVCOST**: provides some diagnostics about the cost function.
- **EWREINI**: write perturbed initial file (ALADIN).
- **FJVARBC**: cost associated with variational bias parameters.
- **FLTMODE**: projection onto subsets of normal modes.
- **GET_TRAJ_SPEC**: reads the trajectory needed for TL and AD model (spectral variables).
- **GRTEST**: test of the cost-function and its gradient.
- **LCNORTL**: operator to localize a perturbation in grid-point space.
- **M1QN3**: minimizer using a quasi-Newton algorithm (can be used to minimize non-quadratic functions).
- **MONIO**: management of the IO events.
- **MONVAR**: management of the 3-D/4-D VAR events.
- **RDFPINC**: reads in the TL trajectory of the model from ARPEGE/GRIB files.
- **READ_TRAJECTORY**: reads the trajectory needed for TL and AD model.
- **SCAAS**: computes the scalar product of two control vectors.
- **SIM4D**: simulator used for example in the 3DVAR and 4DVAR.
- **SPECRT**: computes spectral coefficients of virtual temperature from the spectral coefficients of temperature and moisture (can also do the reverse operation).
- **STEPO**: controls the different phases in a time step.
- **SU1YOM**: initialize level 1 setup.
- **SU2YOM**: initialize level 2 setup.
- **SUALLT**: allocate space for the grid-point and spectral trajectory.
- **SUALLT7**: allocate space for the spectral trajectory of **YOMSPT7**.
- **SUALLAVT**: allocate tables for **AVARC** trajectory minus reference to store them for the minimization.
- **SBSFGS**: subtracts first guess in spectral space to **SPA3**, **SPA2** and **SPA1** arrays.
- **SUCOS**: routine to initialize cost functions.
- **SUGRIDF**: reads the grid-point surface fields on a file.
- **SUGRIDU**: reads the grid-point upper air fields on a file.
- **SUGRIDO**: reads the ocean mixed layer model grid-point fields on a file.
- **SUHDU**: setup for the “unified scheme of horizontal diffusion”.
- **SUHEG**: initialize the solver of the Helmholtz equation in the semi-implicit, in case of stretching and use of geographical divergence.
- **SUHESS**: reads the pre-conditioner used in the minimizers **M1QN3** or **N1CG1**.
- **SUINIF**: routine to initialize the fields of the model.
- **SUJR**: routine to initialize cost function of module **YOMCOSJR**.
- **SUNHSI**: initialize the solver of the Helmholtz equation in the NH model.
- **SURAND2**: initialize stochastic physic parameters: part 2.
- **SUSLB**: initialize pointers of **PTRSLB1** and **PTRSLB2**.
- **SUSPEC**: reads the spectral upper air fields on a file.
- **DEALLT**: release space for the grid-point and spectral trajectory.
- **UPDTIM**: update of the timestep.
- **UPSPEC**: update spectral arrays.

5 List of useful variables.

Only a useful subset of variables are described for the following list of modules and namelists.

5.1 YOMCT0 and NAMCT0.

```
LSIMOB      : .T. = if simulated observations (an analysis or a forecast for example).  
             Option .F. (use of real observations) has not been recently  
             used and validated for configuration 801.  
NCONF       : configuration.  
NFRHIS      : frequency of historical files.  
NHISTS      : array containing historical files events steps.
```

5.2 YOMIOP and NAMTRAJP.

Some of the **YOMIOP** variables are used in configuration 801. The two following variables are used when writing the trajectory (CDCONF(1:1)='T').

```
NPCKFT95    : packing factor; default value is 1 (no packing).  
NEXPBT95    : number of bits used for exponent when packing.
```

These variables are in the namelist **NAMTRAJP**.

5.3 YOMLCZ and NAMLCZ.

Some of the **YOMLCZ** variables are used in configuration 801. They are listed with [U].

```
YVAZXO      [U]: control variable at reference point (vector "delta X").  
YVAZGO      [U]: gradient at reference point (vector of components "delta f/delta x_i").  
YSPFORCE    : ??? (no comment provided in the code).  
RLANBUF     : memory buffer used by Lanczos algorithm.  
GPFORCEU    : ??? (no comment provided in the code).  
GPFORCEV    : ??? (no comment provided in the code).  
GPFORCET    : ??? (no comment provided in the code).  
GPFORCEQ    : ??? (no comment provided in the code).  
GPFORCESP   : ??? (no comment provided in the code).  
RLRAIN      : ??? (no comment provided in the code).  
RITZVALS    : ??? (no comment provided in the code).  
MEMBFGS     : maximum number of (y,s) pairs used to form the BFGS preconditioner.  
NITERL      : maximum number of Lanczos/Jacobi-Davidson(outer) iterations.  
NWEIGL      : maximum number of wanted eigenvalues.  
NLANCOUNT  : counter for the Lanczos iteration.  
NLANTYPE    : type of integration:  
              1: for TL and AD integration  
              2: for TL and AD with covariance matrix constraint  
              3: multiply by covariance matrix only  
NLANNORM    : norm control:  
              1: total energy (default value).  
              2: kinetic energy.  
              3: vorticity**2.  
              4: psi**2.  
              5: rotational kinetic energy  
NEIGEVO     : ??? (no comment provided in the code).  
NLEVMIN     : min level for the local area norm computation  
NLEVMAX     : max level for the local area norm computation  
NWTRMINO    : min total wavenumber of the spectral components not to be set  
              to zero by the spectral truncation, at initial time.  
NWTRMAXO    : max total wavenumber of the spectral components not to be set  
              to zero by the spectral truncation, at initial time.
```

NWTRMIN1 : cf. NWTRMINO but at final time.
 NWTRMAX1 : cf. NWTRMAXO but at final time.
 NEWNORMTO : control the re-definition of the norm at t0:
 1 (resp. 2,3,4,5): to re-define the norm at initial time to be
 total-energy (resp. kinetic energy, vorticity**2, psi**2,
 rotational kinetic energy).
 NINNER : number of Jacobi-Davidson inner iterations.
 NJDSTOP : value of NSTOP used for TL/AD integrations.
 NOPMSTOP : value of NSTOP used in Hessian calculation.
 NRAINSTART : value of NSTEP when accumulation of rain starts.
 N_DIM_SUBSPACE : number of used vectors in 'sv_subspace'.
 NRITZREAD : ??? (no comment provided in the code).
 NRITZNUMB : ??? (no comment provided in the code).
 NRITZGBH1 : ??? (no comment provided in the code).
 NRITZGBH2 : ??? (no comment provided in the code).
 GREDBFGS : required reduction in gradient norm for PCGBFGS.
 XKAPA : acceptable precision for the eigenvalues.
 XMIN_RITZ : smallest accepted eigenvalue for CONGRAD.
 LOCNORM [U]: .T. to localize the norm computation in grid-point space.
 ALAT1 [U]: -|
 ALON1 [U]: |-> coordinates of the local area used for norm computation.
 ALAT3 [U]: | if LOCNORM=.T.
 ALON3 [U]: -|
 NLEVMIN [U]: min level for the local area norm computation if LOCNORM=.T. .
 NLEVMAX [U]: max level for the local area norm computation if LOCNORM=.T. .
 COEQTERM [U]: multiplication coefficient in front of the q-term (specific
 humidity) in the total energy norm scalar weights.
 COENEWQTERM : ??? the same as COEQTERM.
 TSTEP_STATE_4D : ??? (no comment provided in the code).
 LANZCOS : .T. to compute the unstable perturbations.
 .F. to read them from an input file and compute the TL evolution.
 LEVOLC : .T. to write the evolution of the basic state and of some eigenvectors (TL evol).
 LSCALC : .T. to write in the unit NULUSR3 the scalar product weight factors SCALP.
 LSPTRLCO : .T. to truncate the state vector in the spectral space at initial time.
 LSPTRLC1 : .T. to truncate the state vector in the spectral space at final time.
 LSELU [U]: .T. (resp. .F.) to select (resp. ignore) the U-wind in the local norm;
 K_U=1 (resp. 0) in function "f".
 LSELV [U]: .T. (resp. .F.) to select (resp. ignore) the V-wind in the local norm;
 K_V=1 (resp. 0) in function "f".
 LSELT [U]: .T. (resp. .F.) to select (resp. ignore) the temperature in the local norm;
 K_T=1 (resp. 0) in function "f".
 LSELQ [U]: .T. (resp. .F.) to select (resp. ignore) the humidity in the local norm;
 K_q=1 (resp. 0) in function "f".
 LSELSP [U]: .T. (resp. .F.) to select (resp. ignore) the surface pressure in the local norm;
 K_prehyd=1 (resp. 0) in function "f".
 LNEWNORMTO : .T. to re-define the norm at initial time t0.
 LJACDAV : .T. to compute unstable perturbations with the Jacobi-Davidson code.
 LCHSYMEIG : .T. to check eigenvectors and the symmetry of the Hessian.
 LSYMCHECK : ??? (no comment provided in the code).
 LFORCE : .T. to compute Forcing singular vectors:
 unstable perturbations for model tendencies.
 LFORCEWR : ??? (no comment provided in the code).
 LRAIN : .T. to select rain in the final norm (if LSELSP=.F.).
 LRENORMALIZE : .T. to normalize SVs with TE metric at initial time.
 L_USE_CONGRAD : .T. to use CONGRAD Lanczos code. .F. to use LANDR.
 L_UNPREDICTABLE_COMPONENTS: .T. to calculate unpredictable components.
 L_SOS : .T. to compute (finite time integral) stochastic optimals.
 L_EOFS : .T. to compute (finite time integral) EOFs.
 L_BALANCED_REDUCTION: .T. to compute balancing vectors X and Y for model reduction

L_SUBSPACE_SVS : .T. to compute SVs in a subspace orthogonal to a given subspace,
 identified by N_DIM_SUBSPACE vectors in file 'sv_subspace'.
 LMS SIG_SVINI : set SMS event i when initial SVs have been computed
 YSTATE_VECTOR_4D: Array of state vectors (used for balanced reduction).
 YV_SUBSPACE : ??? (no comment provided in the code).
 NSTEPS_PER_STATE: ??? (no comment provided in the code).

Some of them are in the namelist **NAMLCZ**:

5.4 YOMSENS and NAMSENS.

LMINI : .T. if a minimization is required, for example to
 find an optimal initial perturbation.
 Currently works for ARPEGE, not validated for ALADIN.
 Default value is .F.
 LGRVOL : .T. -> activate gradient normalization by SIDE LP to
 write files of 3D density of gradient.
 NJROPT : type of cost function:
 1: quadratic distance to a reference (default value).
 2: linear integral of parameters (available only in ARPEGE).
 3: enstrophy cost-function (available only in ARPEGE).
 LBSENS : use B-matrix in the initial norm.
 Default value is .F.

These variables are in the namelist **NAMSENS**.

5.5 YOMVAR and NAMVAR.

Some of the YOMVAR variables are used in configuration 801.

LGRASCAL : .T. => write gradient with respect to SCALP inner product.
 RDX : starting point for GRTEST.
 NFRREF : frequency of reference observation events;
 it is desirable to have the same values as NFRHIS.
 NREFTS : array containing observation events steps;
 it is desirable to have the same values as NHISTS.
 LWREINI : writes " X_0 - RDX * [adj(M) * [delta Y]_Nstop] "
 on a file; available in ALADIN only.

5.6 YOMVRTL and NAMVRTL.

Some of the YOMVRTL variables are used in configuration 801.

L801TL : .T. = the sensitivity is to be run with the tangent linear model.
 This option is interesting when combined with LMINI=.T.;
 available in ARPEGE only.

6 Example of namelist.

The following namelist is valid for an ARPEGE job with 5 timesteps, resolution TL31L70c1 (linear grid), two-time level semi-Lagrangian advection scheme, no minimization. Complete physics is activated in the direct model (it matches with the physics package which was in the operational suite on 01/10/2011), no physics in the adjoint and tangent linear model. The cost-function is quadratic (**NJROPT=1**) and is computed in all the atmosphere (**LOCNORM=.F.**).

```
&NACIETED
/
&NACOBS
/
&NACTAN
/
&NACTEX
/
&NACVEG
/
&NADOCK
/
&NAEAEM7
/
&NAEAER
/
&NAECOAPHY
/
&NAEPHY
/
&NAERAD
  LRRTM=.TRUE.,
  LSRM=.FALSE.,
  NRADFR=-3,
  NSW=6,
  RLWINHF=0.9,
/
&NAIMPO
/
&NALORI
/
&NAMAFN
  TFP_I%LLGP=.TRUE.,
  TFP_L%LLGP=.TRUE.,
/
&NAMARPHY
/
&NAMCA
/
&NAMCAPE
/
&NAMCFU
  LCUMFU=.TRUE.,
  LFDUTP=.TRUE.,
  LFPLC=.TRUE.,
  LFPLS=.TRUE.,
  LFR=.TRUE.,
  LFSF=.TRUE.,
  LFSOIL=.TRUE.,
  LMOON=.TRUE.,
  LNEBPAP=.TRUE.,
  LSTRD=.TRUE.,
  LSTRT=.TRUE.,
  LFRRC=.TRUE.,
  LRAYD=.TRUE.,
  NFRCFU=1,
  NCFUTS(0)=-1,
  NCFUTS(1)=-97,
/
&NAMCHET
/
&NAMCHK
/
&NAMCLA
/
&NAMCLDP
/
&NAMCLI
/
&NAMCLOP15
/
&NAMCLTC
/
&NAMCOK
/
&NAMCOM
/
```

```

&NAMCOUPL04
/
&NAMCTO
  LARPEGEF=.TRUE.,
  LFBDAF=.FALSE.,
  LFDDBOP=.FALSE.,
  LGUESS=.FALSE.,
  LOBS=.FALSE.,
  LOBSC1=.FALSE.,
  LSIMOB=.TRUE.,
  LTWOTL=.TRUE.,
  LSPRT=.TRUE.,
  LRETFCFOU=.FALSE.,
  LWRTFCFOU=.FALSE.,
  LRFOUTCNORM(1)=.FALSE.,
  LRGPFCNORM(1)=.FALSE.,
  NCNTVAR=1,
  NDHPTS(0)=-1,-999,
  NFRDHP=1,
  NFRHIS=1,
  NFRPOS=10000,
  NFRSDI=1,
  NHISTS(0)=2,
  NHISTS(1)=0,
  NHISTS(2)=5,
  NPOSTS(0)=1,
  NPOSTS(1)=1,
  NSDITS(0)=2,
  NSDITS(1)=0,
  NSDITS(2)=5,
  NSPPR=1,
  NFRISP=1,
  NPISPS(0)=-1,
  NPISPS(1)=-999,
  LALLOPR=.FALSE.,
  LOPT_SCALAR=.FALSE.,
  LREGETA=.FALSE.,
  LVFE_REGETA=.FALSE.,
  LVERTFE=.TRUE.,
  NVSCH=3,
  LAPRXPK=.TRUE.,
  NPRINTLEV=0,
/
&NAMCT1
  LRFILAF=.FALSE.,
  N1POS=0,
  N1RES=0,
/
&NAMCUMF
/
&NAMCUMFS
/
&NAMCVMNH
  OTADJS=10800.,
  XCDEPTH=1.,
  XCDEPTH_D=4000.,
  XDTPERT=0.3,
  XENTR=0.013,
/
&NAMDDH
/
&NAMDFI
/
&NAMDIM
  NPROMA=-469,
  NTCMAX=6,
/
&NAMDIMO
/
&NAMDPHY
/
&NAMDYN
  BETADT=1.,
  RDAMPDIV=5.,
  LDRY_ECMWF=.TRUE.,
/
&NAMDYNA
/
&NAMDYNCORE
/
&NAMEMIS_CONF
/
&NAMENKF
/
&NAMFA
  NBITCS=30,

```

```

NBITPG=30,
NSTRON=-1,
YFAI%NBITS=16,
YFAL%NBITS=16,
YFAR%NBITS=16,
YFAS%NBITS=16,
YFALRAD%NBITS=16,
YFAIRAD%NBITS=16,
YFACLF%NBITS=6,
YFATKE%NBITS=16,
/
&NAMFPC
/
&NAMFPD
/
&NAMFPDY2
/
&NAMFPDYH
/
&NAMFPDYI
/
&NAMFPDYP
/
&NAMFPDYS
/
&NAMFPDYT
/
&NAMFPDYV
/
&NAMFPP
/
&NAMFPG
/
&NAMFPIOS
/
&NAMFPMOVE
/
&NAMFPPHY
/
&NAMFPSC2
/
&NAMFPSC2_DEP
/
&NANGEM
REFLKUO=10000.,
/
&NANGFL
YI_NL%LGPINGP=.TRUE.,
YI_NL%LGP=.TRUE.,
YI_NL%LT1=.TRUE.,
YI_NL%LPHY=.FALSE.,
YI_NL%NREQIN=1,
YI_NL%LREQOUT=.FALSE.,
YI_NL%LADV=.FALSE.,
YI_NL%LQM=.FALSE.,
YL_NL%LGPINGP=.TRUE.,
YL_NL%LGP=.TRUE.,
YL_NL%LT1=.TRUE.,
YL_NL%LPHY=.FALSE.,
YL_NL%NREQIN=1,
YL_NL%LREQOUT=.FALSE.,
YL_NL%LADV=.FALSE.,
YL_NL%LQM=.FALSE.,
YR_NL%LGPINGP=.TRUE.,
YR_NL%LGP=.TRUE.,
YR_NL%LT1=.TRUE.,
YR_NL%LPHY=.FALSE.,
YR_NL%NREQIN=1,
YR_NL%LREQOUT=.FALSE.,
YR_NL%LADV=.FALSE.,
YR_NL%LQM=.FALSE.,
YS_NL%LGPINGP=.TRUE.,
YS_NL%LGP=.TRUE.,
YS_NL%LT1=.TRUE.,
YS_NL%LPHY=.FALSE.,
YS_NL%NREQIN=0,
YS_NL%LREQOUT=.FALSE.,
YS_NL%LADV=.FALSE.,
YS_NL%LQM=.FALSE.,
YTKE_NL%LGPINGP=.TRUE.,
YTKE_NL%LGP=.TRUE.,
YTKE_NL%LT1=.TRUE.,

```

```

YTKE_NL%NREQIN=0,
YTKE_NL%LREQOUT=.FALSE.,
YTKE_NL%NCOUPLING=0,
YTKE_NL%LADV=.FALSE.,
YTKE_NL%LQM=.TRUE.,
YIRAD_NL%LGP=.TRUE.,
YIRAD_NL%NREQIN=0,
YIRAD_NL%LREQOUT=.TRUE.,
YLRAD_NL%LGP=.TRUE.,
YLRAD_NL%NREQIN=0,
YLRAD_NL%LREQOUT=.TRUE.,
YA_NL%LGP=.TRUE.,
YA_NL%NREQIN=0,
YA_NL%LREQOUT=.TRUE.,
/
&NAMGOM
/
&NAMGRIB
/
&NAMGWD
/
&NAMGWMS
/
&NAMHCP
/
&NAMHLOPT
/
&NAMICE
/
&NAMINI
  NEINI=0,
/
&NAMIOMI
/
&NAMIOS
/
&NAMIO_SERV
/
&NAMJBCODES
/
&NAMJFH
/
&NAMJG
/
&NAMJO
/
&NAMLCZ
  LOCNORM=.FALSE.,
  LSELU=.TRUE.,
  LSELV=.TRUE.,
  LSELT=.TRUE.,
  LSELQ=.TRUE.,
  LSELSP=.TRUE.,
  ALON1=355.0,
  ALAT1=50.0,
  ALON3=4.,
  ALAT3=43.0,
  NLEVMIN=1,
  NLEVMAX=31,
/
&NAMLSFORC
/
&NAMMARS
/
&NAMMCC
/
&NAMMCCUF
/
&NAMMKODB
/
&NAMMODERR
/
&NAMMTS
/
&NAMMWAVE
/
&NAMNMI
/
&NAMNPROF
/
&NAMNUD
/
&NAMOBS
/
&NAMONEDVAR
/

```

```

&NAMOPH
  LINC=.TRUE.,
  CFNHWF='ECHIS',
/
&NAMOPTCMEM
/
&NAMPARO
  NPROC=1,
  NPRGPN=1,
  NPRTRW=1,
  NPRGPEW=1,
  NPRTRV=1,
  NOUTPUT=1,
  MP_TYPE=2,
  MBX_SIZE=12800000,
/
&NAMPAR1
  LSPLIT=.FALSE.,
  NSTRIN=1,
  NSTROUT=1,
  NCOMBFLEN=1638400,
  LEQ_REGIONS=.FALSE.,
/
&NAMPARAR
/
&NAMPHMSE
/
&NAMPHY
  CGMIXLEN='AY',
  LAERODES=.TRUE.,
  LAEROLAN=.TRUE.,
  LAEROSEA=.TRUE.,
  LAEROSOO=.TRUE.,
  LCONDWT=.TRUE.,
  LDIFCONS=.TRUE.,
  LFPCOR=.TRUE.,
  LNEWWD=.TRUE.,
  LNOIAS=.TRUE.,
  LO3ABC=.TRUE.,
  LPROCLD=.TRUE.,
  LRAY=.FALSE.,
  LRAYFM=.TRUE.,
  LRAYLU=.TRUE.,
  LRNUMX=.TRUE.,
  LSSD=.TRUE.,
  LSTRA=.FALSE.,
  LVGSN=.TRUE.,
  LCVPPKF=.TRUE.,
  LECDEEP=.TRUE.,
  LECSHAL=.TRUE.,
  LECT=.TRUE.,
  LFLUSO=.TRUE.,
  LNEBECT=.FALSE.,
  LNSMLIS=.FALSE.,
  LO3FL=.TRUE.,
  LECTFL=.TRUE.,
  LZOHSREL=.TRUE.,
  LADJCLD=.TRUE.,
  NCALLRAD=2,
  NDPSFI=0,
/
&NAMPHYO
  EDD=1.,
  EDK=1.,
  GCVNU=5.E-05,
  GCVPSI=1.,
  GCVPSIE=1.,
  GWDGD=5.4,
  GWDSE=0.005,
  GWDVALI=0.5,
  QSNEEC=-1.,
  QSSUSC=5.,
  RCVEVAP=0.25,
  REVASX=2.E-07,
  RICRLM=0.5,
  TDDGP=0.6,
  TUDGP=0.6,
  USURIC=0.175,
  USURICL=1.,
  USURID=0.1,
  VZOCM=1.0E-4,
  XBLM=8.5,
  XMAXLM=5000.,
  XMINLM=10.,
  ALMAVX=1000.,
  GCVHMIN=30000.,
  RFACNSM=1.2,
  RFLCHCE=0.25,

```

```

RKFBTAU=3600.,
RPRTH=1.,
RQICRT2=0.,
RQICVMIN=1.E-5,
SXNBCO=1.,
ALMAVE=0.,
RQCRNS=0.,
RQICRSN=1.,
TFVI=0.08,
TFVL=0.02,
TFVS=1.5,
GCVOMGE=2.,
GCVOMGQ=1.,
/
&NAMPHY1
ALBMIN=0.65,
ALCRIN=0.75,
EMMGLA=0.98,
EMMMER=0.99,
/
&NAMPHY2
FACRAF=3.5,
XMULAF=0.,
LRAFTKE=.TRUE.,
HTKERAF=20.0,
/
&NAMPHY3
/
&NAMPHYDS
/
&NAMPONG
/
&NAMPPC
/
&NAMPRE
/
&NAMRAD15
/
&NAMRADCMEM
/
&NAMRCF
/
&NAMRCOEF
/
&NAMRES
/
&NAMRGRI
/
&NAMRINC
/
&NAMRIP
/
&NAMSATS
/
&NAMSCC
/
&NAMSCEN
/
&NAMSCM
/
&NAMSEKF
/
&NAMSENS
LGRVOL=.TRUE.,
NJROPT=1,
/
&NAMSIMPHL
/
&NAMSKF
/
&NAMSPSDT
/
&NAMSTA
/
&NAMSTOPH
/
&NAMSWE
/
&NAMTESTVAR
/
&NAMTLEVOL
/
&NAMTOPH
ETCVIM=5000.,
ETNEBU=5000.,
ETPLUI=5000.,
XDRMTK=2.E-08,
XDRMTP=800.,

```

```

XDRMTX=4.E-07,
XDRMUK=1.E-07,
XDRMUP=800.,
XDRMUX=2.E-06,
/
&NAMTRAJP
NPCKFT95=1,
/
&NAMTRANS
/
&NAMTS
/
&NAMVAR
LREFINC=.FALSE.,
LTEST=.FALSE.,
LGRASCAL=.TRUE.,
RDX=0.1,
NFRREF=1,
NREFTS(0)=1,
NREFTS(1)=5,
LJCNMTL=.FALSE.,
LJCNMI=.FALSE.,
LWREINI=.FALSE.,
/
&NAMVARBC
/
&NAMVARBC_AIREP
/
&NAMVARBC_ALLSKY
/
&NAMVARBC_GBRAD
/
&NAMVARBC_RAD
/
&NAMVARBC_SFCOBS
/
&NAMVARBC_TCWV
/
&NAMVARBC_T03
/
&NAMVAREPS
/
&NAMVDOZ
/
&NAMVFP
/
&NAMVRTL
L801TL=.FALSE.,
/
&NAMVVO
/
&NAMVV1
/
&NAMVWRK
/
&NAMWAVELETJB
/
&NAMXFU
LXCLP=.TRUE.,
LXCLS=.TRUE.,
LXFU=.TRUE.,
LXHHCLS=.TRUE.,
LXICV=.TRUE.,
LXNEBPA=.TRUE.,
LXNEBTT=.TRUE.,
LXQCLS=.TRUE.,
LXSOLL=.TRUE.,
LXTGST=.TRUE.,
LXTTCLS=.TRUE.,
LXXGST=.TRUE.,
NFRXFU=1,
NXFUTS(0)=-1,
NXFUTS(1)=-97,
/
&NAM_CANAPE
/
&NAM_DISTRIBUTED_VECTORS
/
&NAPHLC
LSPHLC=.FALSE.,
LVDFLC=.FALSE.,
LVDFDS=.FALSE.,
LSDRDS=.FALSE.,
LZMCON=.FALSE.,
LKEXP=.FALSE.,
/
&NEMCTO

```



```
/
&NEMDIM
/
&NEMDYN
/
&NEMELBCOA
/
&NEMELBCOB
/
&NEMFPEZO
/
&NEMGEO
/
&NEMJK
/
&NEMVAR
/
&NEMWAVELET
/
```

In the command line one finds:

```
NCONF=801
VERSION=meteo
CNMEXP=[cojo]
TSTEP=900.
NSTOP=t5
ADVEC=sli
```

The following files must be provided: ICMSH[cojo]INIT (initial file), ICMSH[cojo]IMIN (copy of ICMSH[cojo]INIT), ICMRF[cojo]0000 (forecast or analysis at timestep N_{stop}).

7 References and internal notes.

7.1 Publications.

- Courtier, Ph., C. Freydl, J.F. Geleyn, F. Rabier and M. Rochas, 1991: The ARPEGE project at METEO-FRANCE. ECMWF Seminar Proceedings 9-13 September 1991, Volume II, 193-231.
- Rabier, F., E. Klinker, Ph. Courtier and A. Hollingsworth, 1996: Sensitivity of forecast errors to initial conditions. *Quart. J. Roy. Meteor. Soc.*, **122**, 121-150.
- Soci, C., A. Horányi and C. Fischer, 2003: Preliminary results of high resolution sensitivity studies using the adjoint of the ALADIN mesoscale numerical weather prediction model. *Quarterly Journal of the Hungarian Meteorological Service*, **107 nr 1**, 49-65.

7.2 Some internal notes and other ARPEGE notes.

- (TDECDA) 2010: IFS technical documentation (CY36R1). Part II: data assimilation.
- (TDECTEC) 2010: IFS technical documentation (CY36R1). Part VI: technical and computational procedures. Available at “<http://www.ecmwf.int/research/ifsdocs/>”.
- (ID801O) Bouttier, F., 1995: Sensitivity jobs with configuration 801. Internal documentation valid for cycle 13r3, 13pp, available on the intranet server “<http://gco.meteo.fr/ifsdoc/html/>”.
- (IDVAR) Fischer, C., and L. Berre, 2007: The variational computations inside ARPEGE/ALADIN: cycle CY32. Internal note, 77pp. Available on the intranet server “<http://www.cnrm.meteo.fr/gmapdoc/>”.
- (NTA28) Rabier, F., Ph. Courtier, O. Talagrand et J.F. Geleyn, 1992: Two applications of adjoint models to sensitivity analysis. Note de travail ARPEGE numéro **28**, 44pp.
- (IDBAS) Yessad, K., 2011: Basics about ARPEGE/IFS, ALADIN and AROME in the cycle 38 of ARPEGE/IFS (internal note).
- (IDEUL) Yessad, K., 2011: Integration of the model equations, and Eulerian dynamics, in the cycle 38 of ARPEGE/IFS (internal note).
- (IDDM) Yessad, K., 2011: Distributed memory features in the cycle 38 of ARPEGE/IFS (internal note).
- (IDMINI) Yessad, K., 2011: Minimizations in the cycle 38 of ARPEGE/IFS (internal note).